Sport In The Box Support

Knowledgebase > Common questions > How to setup SITB2 with Hytek

How to setup SITB2 with Hytek

Erik Berglund - 2021-04-26 - Comments (0) - Common questions

To configure SITB2 with Hytek using UDP port go to:

ne	Repo	rts	La	bels	Pre	ferences	Interface	s OW Module	Meet Mobile	н	lelp		
					Set-up			>		Timing Console Interface - Pool 1			
					Timer (None) Pool 1			>		Scoreboard - Pool 1	E		
-	F	VFN	πı	IST .	All F	vents - SC	Sco	reboard (GENSER) Pool 1	>		Open Water Button Timer	
н		_	_	_	DFS			reboard2		>]			_
	10	•			-		Dolphin Backup Mode		>				
	5	-	-	-	-						l I		
	11	-	1	2	-								
	5	-	-	-	-								
	12	_	4										

Set it to Generic and UDP. (Also possible to use serial but then you need a serial connection between Hytek computer and SITB2).

	Select Your Scoreboar	rd														
Scoreboard 1 - Pool 1 C Colorado Timing System C Daktronics C Omega																
								Generic								
								C Network File Sharing IST or Quantum-AQ C None								
																Connection Method
UDP Ethernet																
	1	1														
	QK Cancel															


You also need to change IP adress here:

The selected address should be the one of the SITB2 computer.

	Interfaces OW Module Meet Mobile	H	lelp	
	Set-up	>	1	
	Timer (None) Pool 1	>		НΥ
	Scoreboard (GENSER) Pool 1	>	Set UDP Port and IP Address	
1	Scoreboard2	>	Customize	
	Dolphin Backup Mode	÷		

😂 Set UDP Port and	IP Address		-	0	×
	UDP - Gr	eneric UDP			
Remote Scor	eboard Port / S	iocket (1 to 65	535) :	25252	_
	Remote Score	board IP Addr	ess: 1	92.168.1.	255
Enter 255.255.255.	255 for UDP IP a	iddess to broa	adcast to a	ill local If	°s
	ок	Cancel	1		

And check:



Best Regards

Erik